

The ZCPR3 INSTALLATION WORKBOOK

by Richard Conn

First Revision, 8 March 1985
Original Draft, 20 February 1985

About this Workbook

This workbook takes you through the eight steps of ZCPR3 installation. You should have a copy of the Installation Manual (or SAMPLER) handy as you work through it. This workbook will serve to direct your reading of the Installation Manual and provide a place for you to write down information required during the installation process. There are blanks to fill in and scratch areas in which you may perform computations and make notes; it is recommended that you make all of your computations and notes here. This workbook can serve as a document on how you set up your ZCPR3 system, so you can refer back to it later if you want to make a change.

Each step of the installation process is detailed in the following pages and is presented with the following format:

Objective:

The goal to be achieved

Required Files:

The programs and other files required to perform this step

References:

The chapters and sections in the Installation Manual and in ZCPR3: The Manual associated with this step; the indicated sections of the Installation Manual are required reading, while those sections in ZCPR3: The Manual contain supplementary information

Instructions:

Step-by-step details on what to do; places are also provided for you to write down important information

Overview of ZCPR3 Installation

Objective To summarize the goals of the installation process

Required Files None

References

Installation Manual -- Chapter 1
ZCPR3: The Manual -- Chapters 1, 2, 9-16

Instructions

1. Review chapter 1 of the Installation Manual and (optionally) review the indicated chapters of ZCPR3: The Manual.

2. In summary, the following items are going to be created for your microcomputer system.

A. A new SYSGEN image containing the ZCPR3 Command Processor in place of the CP/M Console Command Processor (CCP). The BIOS may also be modified. Figure 1-1 (page 6) of the Installation Manual shows the SYSGEN images of a conventional CP/M system and a ZCPR3 system. The modified BIOS is required in order to initialize the ZCPR3 buffers for your system.

B. The System Segments required for your choice of ZCPR3 configuration. Section 1.3 of the Installation Manual (page 7) and chapters 2, 10, and 16 of ZCPR3: The Manual discuss the topic of the System Segments. The ZCPR3 System Segments are:

- o Environment Descriptor
- o TCAP File for your terminal
- o Flow Command Packages
- o Input/Output Packages
- o Resident Command Packages
- o Named Directory Files

C. The ZCPR3 Utilities installed for your ZCPR3 configuration. Section 1.4 of the Installation Manual (page 7) and chapters 3-8, 15, and 16 of ZCPR3: The Manual discuss the utilities.

3. The installation process for a ZCPR3 system consists of these steps:

- 1) Select the features of the target ZCPR3 system
- 2) Plan the memory structure of the target ZCPR3 system
(create Z3BASE.LIB)
- 3) Modify the cold boot routine in the BIOS to
initialize buffers as required
- 4) Select the features of the ZCPR3 Command Processor
(create Z3HDR.LIB)
- 5) Overlay the CP/M CCP with the ZCPR3 Command
Processor and overlay the old BIOS with the
new BIOS; create the new SYSGEN image for your
ZCPR3 System
- 6) Place the new SYSGEN image for your ZCPR3 System
onto the Operating System tracks of a disk
- 7) Select the features of your System Segments and
create the System Segments
- 8) Install the ZCPR3 utilities

Read chapter 1 of the Installation Manual now.

Step 1: Selecting the Features

Objective Select the features your ZCPR3 System will have

Required Files None

References

Installation Manual -- Chapter 2
ZCPR3: The Manual -- Chapters 2, 9-11, and 17

Instructions

A. Read Chapter 2 of the Installation Manual.

B. Make the following decisions:

1. Are you going to include the standard overhead in your ZCPR3 System? It is recommended that you answer YES to this question. If YES, go to decision 3; if NO, go to question 2.

2. You are NOT going to include the standard 1K overhead in your ZCPR3 System. Which parts of the standard overhead are you going to include?

- 2a. External Stack YES NO
- 2b. Command Line Buffer YES NO
- 2c. Memory-Based Named Directory YES NO
- 2d. External File Control Block YES NO
- 2e. Message Buffers YES NO
- 2f. Shell Stack YES NO
- 2g. Environment Descriptor YES NO

3. Which of the following packages are you going to implement in your ZCPR3 System? It is suggested that Flow Command Packages are most important, Resident Command Packages are second, and Input/Output Packages are third.

- 3a. Flow Command Packages YES NO
- 3b. Resident Command Packages YES NO
- 3c. Input/Output Packages YES NO

The ZCPR3 INSTALLATION WORKBOOK

4. Which of the other buffers are you going to provide?
The External Path is highly recommended.

4a. External Path	YES	NO
4b. Wheel Byte	YES	NO

-- Blank Space for Comments --

Step 2: ZCPR3 Memory Structure

Objective To plan the memory structure of your ZCPR3 System and to create your Z3BASE.LIB file

Required Files Z3BASE.LIB (ZCPR3 File)
Z3LOC.COM (ZCPR3 File)
MOVCPM.COM or equiv
DDT.COM or equiv (ZDM and DSD)
your favorite editor

References
Installation Manual -- Chapter 3
ZCPR3: The Manual -- Chapters 2 and 18

Instructions
A. Read Chapter 3 of the Installation Manual.

B. You are now going to figure out how much space your ZCPR3 System is going to take. Fill out the following table based on your answers in Step 1.

1. If you answered YES to question 1, enter 1K and go on to the bottom of the page. If you answered NO to question 1, enter 0 and go on to question 2.

2. For each of the YES answers under question 2, enter the indicated value. For each of the NO answers, enter 0. Items 2b, 2c, and 2f may be adjusted if you want more or less space.

- 2a. External Stack = 48 _____
- 2b. Command Line Buffer = 208
(allows for 200 chars/line) _____
- 2c. Named Directory Buffer = 256
(allows for 14 18-byte entries) _____
- 2d. External FCB = 48 _____
- 2e. Message Buffers = 80 _____
- 2f. Shell Stack = 128
(allows for 4 32-byte shells) _____
- 2g. Environment Descriptor = 256 _____

Compute the total of all values you have entered in on this page. =====

The ZCPR3 INSTALLATION WORKBOOK

2h. Enter the total from the bottom of the previous page here.

=====

3. Enter the following values for each of the packages you selected in question 3 in step 1. If you wish to modify these values to provide more or less space for each of these packages, feel free to do so. The indicated sizes are the recommended values.

3a. Flow Command Package = 0.5K _____

3b. Resident Command Package = 2K _____

3c. Input/Output Package = 1.5K _____

3d. Total of 3a-3c =====

4. Items 4a and 4b in step 1 require virtually no additional space (on the order of 10-16 bytes total), and space for these entries can usually be found somewhere in fixed memory (down in the first 256 bytes or up in the BIOS). No space entry will be made for these selections.

Compute the total of the entries on this page and round the number up to the next 1K if there is any fraction. Enter the total of 2h and 3d. =====

C. Figure out the size of your BIOS. The program Z3LOC will give you the starting address of your BIOS if you run it on your current system. As an alternative, the address at memory locations 1 and 2 can be examined with DDT to determine where your BIOS starts. Write down the size of your BIOS here.

The ZCPR3 INSTALLATION WORKBOOK

D. Determine where you can place the ZCPR3 Command Processor (ZCPR3 CP). This hinges on where your MOVCPM (or equivalent) program places the system when told to move it. MOVCPM relocates the BDOS for you, and this is the one part of your old CP/M system which we are retaining, so we will have to plan the memory map of your system based on where you can place the BDOS. If you are going to use ZRDOS1 or ZRDOS2 from Echelon, this becomes much less of a problem since you have absolute control of where you can place the ZRDOS. Since the installation manual is geared for those who will continue to use the CP/M BDOS, we will direct the discussion to the BDOS and not cover installation with ZRDOS at this time.

To assist you further in determining the addresses for the components of your ZCPR3 System, the following table shows the addresses of the ZCPR3 Command Processor, BDOS, and BIOS for various sizes of TPA (by "TPA", I am referring to the area of memory below the ZCPR3 Command Processor which does NOT include the ZCPR3 Command Processor itself).

<u>TPA Size</u>	<u>Locations</u>		
	<u>ZCPR3 CP</u>	<u>BDOS</u>	<u>BIOS</u>
44K	0B000	0B800	0C600
45K	0B400	0BC00	0CA00
46K	0B800	0C000	0CE00
47K	0BC00	0C400	0D200
48K	0C000	0C800	0D600
49K	0C400	0CC00	0DA00
50K	0C800	0D000	0DE00
51K	0CC00	0D400	0E200
52K	0D000	0D800	0E600
53K	0D400	0DC00	0EA00
54K	0D800	0E000	0EE00
55K	0DC00	0E400	0F200
56K	0E000	0E800	0F600

For example, if the amount of additional overhead, as indicated by your answer to question B4 on the previous page, is 1K, and your BDOS currently resides at E400, then you need to move the BDOS down by 1K (1K = 400H) to E000. Hence, you need to run MOVCPM with the correct value to place your BDOS at a starting address no higher than E000.

Find this value now. Record the following values:

ZCPR3 CP Address _____
 BDOS Address _____
 BIOS Address _____

The ZCPR3 INSTALLATION WORKBOOK

E. Using the memory map in Figure 3-1 (page 22) of the Installation Manual and the examples on the following two pages as a guide, fill out the following table as a memory map for the system you are planning. Use the data from Step 1 and the questions in this step (A-D) to help you. The answers from question D (previous page) should be copied directly into this table as they are (starting addresses of the ZCPR3 CP, BDOS, and BIOS). Leave blank the elements you did not select. If your ROM is at an odd location, adjust your memory usage accordingly (you may want to place some of the buffers AFTER the ROM).

<u>FUNCTION</u>	<u>SIZE</u>	<u>ADDRESS</u>	
		<u>STARTING</u>	<u>ENDING</u>
ZCPR3 Command Processor	2 K	_____	_____
BDOS	3.5 K	_____	_____
Your BIOS	_____	_____	_____
ROM (if not at top of memory)	_____	_____	_____
Resident Command Package	_____	_____	_____
ROM (if not at top of memory)	_____	_____	_____
Input/Output Package	_____	_____	_____
ROM (if not at top of memory)	_____	_____	_____
Flow Command Package	_____	_____	_____
ROM (if not at top of memory)	_____	_____	_____
Environment Descriptor	_____	_____	_____
Shell Stack	_____	_____	_____
Message Buffers	_____	_____	_____
External FCB	_____	_____	_____
Named Directory Buffer	_____	_____	_____
Command Line Buffer	_____	_____	_____
External Stack	_____	_____	_____
ROM (if at top of memory)	_____	_____	_____

See the following two pages for examples of how to fill in this table. Refer also to page 22 of the Installation Manual.

Example 1: No ROM in memory and no Input/Output Package. All other features selected.

<u>FUNCTION</u>	<u>SIZE</u>	<u>ADDRESS</u>	
		<u>STARTING</u>	<u>ENDING</u>
ZCPR3 Command Processor	2 K	_ D600 _	_ DDFF _
BDOS	3.5 K	_ DE00 _	_ EBFF _
Your BIOS	__ 1.5 K	_ EC00 _	_ F1FF _
ROM (if not at top of memory)	_____	_____	_____
Resident Command Package	__ 2.0 K	_ F200 _	_ F9FF _
ROM (if not at top of memory)	_____	_____	_____
Input/Output Package	_____	_____	_____
ROM (if not at top of memory)	_____	_____	_____
Flow Command Package	__ 0.5 K	_ FA00 _	_ FBFF _
ROM (if not at top of memory)	_____	_____	_____
Environment Descriptor	_ 256 _	_ FC00 _	_ FCFF _
Shell Stack	_ 128 _	_ FD00 _	_ FD7F _
Message Buffers	_ 80 _	_ FD80 _	_ FDCF _
External FCB	_ 48 _	_ FDD0 _	_ FDFE _
Named Directory Buffer	_ 256 _	_ FE00 _	_ FEFF _
Command Line Buffer	_ 208 _	_ FF00 _	_ FFCE _
External Stack	_ 48 _	_ FFD0 _	_ FFFF _
ROM (if at top of memory)	_____	_____	_____

Example 2: 1K ROM from F800-FBFF and no Input/Output Package.
All other features selected.

<u>FUNCTION</u>	<u>SIZE</u>	<u>ADDRESS</u>	
		<u>STARTING</u>	<u>ENDING</u>
ZCPR3 Command Processor	2 K	_ D200 _	_ D9FF _
BDOS	3.5 K	_ DA00 _	_ E7FF _
Your BIOS	___ 1.5 K	_ E800 _	_ EDFD _
ROM (if not at top of memory)	_____	_____	_____
Resident Command Package	___ 2.0 K	_ EE00 _	_ F5FF _
ROM (if not at top of memory)	_____	_____	_____
Input/Output Package	_____	_____	_____
ROM (if not at top of memory)	_____	_____	_____
Flow Command Package	___ 0.5 K	_ F600 _	_ F7FF _
ROM (if not at top of memory)	___ 1.0 K	_ F800 _	_ FBFF _
Environment Descriptor	_ 256 _	_ FC00 _	_ FCFF _
Shell Stack	_ 128 _	_ FD00 _	_ FD7F _
Message Buffers	_ 80 _	_ FD80 _	_ FDCF _
External FCB	_ 48 _	_ FDD0 _	_ FDFD _
Named Directory Buffer	_ 256 _	_ FE00 _	_ FEFF _
Command Line Buffer	_ 208 _	_ FF00 _	_ FFCD _
External Stack	_ 48 _	_ FFD0 _	_ FFFF _
ROM (if at top of memory)	_____	_____	_____

F. You now have all the data required to edit Z3BASE.LIB. Run your favorite editor on Z3BASE.LIB:

1. Edit the comment header and fill in the values for your system as presented in the table you just filled in above. You will find this to be a tedious process which really pays off in the long run.

2. Set all of the equates in Z3BASE.LIB to contain the proper values as you planned on the table above. Follow through section 3.3 of the Installation Manual as you do this.

-- Blank Space for Calculations and Notes --

Step 3: Modify the BIOS Cold Boot Routine

Objective Modify the Cold Boot routine in your BIOS to initialize the buffers you selected above.

Required Files source to your BIOS
 your favorite editor
 an assembler that will assemble your BIOS and generate a HEX file

References

Installation Manual -- Chapter 4, Section 4.1
 ZCPR3: The Manual -- Chapter 19

Instructions

A. Study section 4.1 of Chapter 4 of the Installation Manual. Refer to the sample session in section 4.5.

B. Write code into the Cold Boot routine to initialize the buffers you included in your ZCPR3 System. You may want to use the code in section 4.1 after the label CBOOT: as a model for your code.

The following buffers must be initialized to zero:

1. Resident Command Package
2. Flow Command Package
3. Environment Descriptor
4. Shell Stack
5. Message Buffers
6. Named Directory Buffer

The following buffers must be initialized with data:

1. External Path
 Initialize the path
2. Wheel Byte
 Clear it or set it
3. Input/Output Package
 Place initial set of drivers
4. Command Line Buffer
 Initialize size and startup command

The following buffers do not need to be initialized:

1. External Stack
2. External File Control Block

C. Assemble your BIOS and make sure it assembles without error. Also make sure that it is small enough to fit on the System Tracks for your microcomputer. You now have a HEX file of your new BIOS.

Step 4: Editing Z3HDR.LIB

Objective To select the features of the ZCPR3
Command Processor

Required Files Z3HDR.LIB (ZCPR3 File)
Z3BASE.LIB (ZCPR3 File)
ZCPR3.ASM (ZCPR3 File)
your favorite editor
Digital Research MAC, Echelon ZAS,
or equivalent assembler

References

Installation Manual -- Chapter 4, Section 4.2
ZCPR3: The Manual -- Chapters 2, 9, and 19

Instructions

A. Read section 4.2 of the Installation Manual. Refer to the sample session in section 4.5.

B. Edit Z3HDR.LIB and set the equates as you desire. Follow along in section 4.2 of the Installation Manual since it provides a running dialog of your basic tradeoffs.

C. Assemble ZCPR3 and make sure it assembles without error. This automatically checks to ensure that the ZCPR3 Command Processor is 2K or less in size (an error is raised if it is over 2K in size). You have to use an assembler like Echelon's ZAS because of the use of macros. You now have a HEX file of your ZCPR3 Command Processor.

Step 5: Overlaying the old BIOS and the CCP

Objective Replace the CP/M CCP with ZCPR3 and your old BIOS with the modified BIOS created above.

Required Files MOVCPM.COM
 SYSGEN.COM
 DDT.COM, SID.COM, or equivalent
 ZCPR3.HEX (from previous assembly)
 BIOS.HEX (from previous assembly)

References

Installation Manual -- Chapter 4, Section 4.3
 ZCPR3: The Manual -- Chapter 19

Instructions

A. Read section 4.3 of the Installation Manual. Refer to the sample session in section 4.5.

B. You may want to build a conventional CP/M system which contains your new BIOS and runs at the address of your new ZCPR3 system. This is an additional step which is not detailed in the Installation Manual at this point, and it may save you a lot of frustration later. Among other things, it assures you that your BIOS is correct and that your BOOT is also working properly. To do this:

1. Run MOVCPM with the proper value
2. SAVE the memory image to a disk file (CPM.BIN)
3. Run DDT on CPM.BIN to load it
4. Load the BIOS (section 4.5.11 shows the procedure)
5. Correct the BOOT if necessary
6. Exit DDT and SAVE the result to disk
7. Run SYSGEN on the new image, place it on the system tracks, and make sure it boots and runs correctly

If you do this part of Step 5, you now have a working CP/M system which runs where your ZCPR3 will run, and you have confirmed that your BIOS is OK. You are also in a good place to follow the Installation Manual at step 4.5.10.

C. If you did not do B above, run MOVCPM on your current CP/M System to locate the BDOS at the proper location. Save the resultant system image on disk as a file via the SAVE command. If you did B above, the image generated is ready for you.

D. Use DDT to read in the system image saved in B or C. Examine the area occupied by the CCP and BDOS to make sure they are where they should be.

E. Still in DDT: Zero out the area occupied by the CCP. Use the I and R commands to read in the HEX file of the ZCPR3 Command Processor. Follow along in section 4.5.11 of the Installation Manual if you need to.

F. Still in DDT: Zero out the area occupied by the BIOS. Use the I and R commands to read in the HEX file of the BIOS. Follow along in section 4.5.11 of the Installation Manual if you need to.

G. Exit DDT and save this new system image on disk as a file. I will refer to this file as ZCPR3.BIN.

-- Blank Space for Calculations --

Step 6: Implanting the Operating System Image

Objective Place the image created above on the operating system tracks of a scratch disk.

Required Files DDT.COM
SYSGEN.COM
ZCPR3.BIN

References

Installation Manual -- Chapter 4, Section 4.4
ZCPR3: The Manual -- Chapter 19

Instructions

A. Read section 4.4 of the Installation Manual. Refer to the sample session in section 4.5.

B. Use DDT (I and R commands) to load the system image file (ZCPR3.BIN) into memory. Check it to make sure that all is well. As a minimum, make sure the following is true:

1. The ZCPR3 Command Processor is in place and the addresses within it are correct.
2. The BIOS is in place and the addresses within it are correct.
3. The BOOT is correct for loading the operating system at the correct memory location.

C. Use SYSGEN to place this memory image onto the operating system tracks of a scratch disk. Section 4.5.12 in the Installation Manual gives you an example of this step.

D. Remove all disks from your system. Place the scratch disk in your A drive and try to boot it.

If all went well, ZCPR3 should have come up and presented you with a prompt. Since your scratch disk is blank, if you loaded the Command Line Buffer with a STARTUP command, ZCPR3 should have echoed this command followed by a question mark to indicate that it was not found.

Step 7: System Segment Installation

Objective Install the System Segments your selected.

Required Files LIB and ASM files for the System Segments:

SYSRCP.LIB and SYSRCP.ASM
SYSFCP.LIB and SYSFCP.ASM
SYSIOP.LIB and SYSIOP.ASM
SYSNDR.LIB and SYSNDR.ASM
SYSENV.LIB and SYSENV.ASM
your favorite editor
MAC.COM or equivalent
MLOAD.COM or equivalent

References

Installation Manual -- Chapter 5
ZCPR3: The Manual -- Chapter 20

Instructions

A. Read Chapter 5 of the Installation Manual.

B. Edit the LIB files to select the features for your System Segments. Chapter 5 provides a running commentary of your options, and you may find it useful to follow along in the appropriate section of Chapter 5 as you edit each LIB file. The following sections of Chapter 5 cover the indicated segments:

5.1 - Resident Command Packages
5.2 - Flow Command Packages
5.3 - Input/Output Packages
5.4 - Named Directory Files
5.5 - TCAP Files
5.6 - the Environment Descriptor

C. Assemble your System Segments. Make sure they assemble without error. Give the assembled object files the proper file types. Sections 4.5.1 to 4.5.7 provide overviews of this process and may prove useful.

Chapter 7 of the Installation Manual goes into some detail on the TCAP and how to create your own if one is not already available via the TCSELECT program.

Also note that you may later want to run some of the ZCPR3 utilities to edit and create new named directory files.

Step 8: Utility Installation

Objective Install the ZCPR3 Utilities for your system

Required Files Z3INS.COM
an INS file naming the utilities
your favorite editor
the utilities (COM files) you want to install

References

Installation Manual -- Chapter 6
ZCPR3: The Manual -- Chapter 21

Instructions

- A. Read Chapter 6 of the Installation Manual.
- B. Use your favorite editor to create an INS file if you do not already have one. Place the names of the files to be installed in this file, one file per line.
- C. Place all files to be installed, Z3INS.COM, your Environment Descriptor file, and your INS file in the same directory on disk. Run Z3INS on your INS file and your Environment Descriptor file.
- D. Optionally create a TCAP file if you have not already done so (see Chapter 7 of the Installation Manual).
- E. Place all of your system files in the root directory, create the STARTUP alias if you need one, and boot your new ZCPR3 System.

CONGRATULATIONS!